


1. GE PLC - CIMPLICITY 8.2:

Start Option for Proficy Software

Start Menu ==> Proficy HMI SCADA - CIMPLICITY 8.2




Proficy HMI SCADA - CIMPLICITY 8.2 ==> PCIM Configuration

PCIM Configuration ==> Select Layout GAIL.gef



Proficy HMI SCADA - CIMPLICITY 8.2 Workbench Version



Proficy HMI SCADA - CIMPLICITY 8.2 Alarm Print Option

Alarm Print ==> Select New on Right Click ==> Give Proper Name (i.e XAIMS_Print)

Alarm Print ==> General Option ==>

- Check mark All in General Option (i.e. Log Event, log alarm, general alarms)
- Output ==> \\Localhost\AIMS(Virtual Printer Name)

